



TDM5 - How to change the resolution of a PowerPoint

# Introduction

TDM5 has the option to import PowerPoint's, in default the slides are set to a low resolution. In this manual we will explain how to change the slide size so these get imported a higher resolution.

# Requirements

If you want to change a PowerPoint's slide size you need to meet the following requirements:

- Have a PowerPoint presentation to import
- Have access to the TDM5 designer


# How To change the resolution of a PowerPoint

1. Open the PowerPoint presentation.


2. Navigate to the “Design” tab.



3. On the right select “Slide Size”.




4. Open the “Slides sized for” and select “Custom”.




5. Now we can change the “Width” and “Height” of the slides, this is set in CM so we need to convert the resolution from pixels to CM.

- 1920x1080 = Width: 67.729 CM / Height: 38.1 CM
- 3840x2160 = Width: 101.6 CM / Height: 57.15 CM

6. Select the desired Width and Height and select “OK”.



7. Navigate to TDM5 and select “Media”.



8. Select the "Upload" button and choose the desired PowerPoint file.

## Media



9. You have now successfully uploaded a PowerPoint presentation with custom Slides sizes.